



Using the iPad Reviewer App

- The App requires a .vcreview file created by VERICUT 7.3 (and 7.3.x).
- The App shows workpiece view and machine view.
- The App does not show “replace material” even if it is saved in the .vcreview file (not recommended). “Replace material” makes the file significantly larger.
- If you save a report .pdf before saving the .vcreview file, then the .pdf file will be included with the .vcreview file. The App has a button to view a report .pdf embedded in the review file contents.
- The App Displays one View at time. The default view when opening the App is whatever **View 1** was (machine/CutStock or Workpiece) when the .vcreview file was saved.
- The App only runs in Open-GL. You can control of the **Cut Stock Display** in the App Settings menu.
- Suggested VERICUT Properties settings when creating a .vcreview file for an iPad:



Uploading files to your iPad


- Via iTunes
 - Connect the iPad to your computer with a cable and open iTunes.
 - Select your iPad from the top menu:




- Once you login to your iPad Select Apps




- Scroll Down to File Sharing, and select Reviewer:



○ Then select the share icon  then choose “Open in...”



○ Then select Reviewer



- Via Email

- If you get E-mail on your iPad, simply E-mail yourself a Reviewer file and open it using the same steps as DropBox